



# Fleekdrive Desktop update procedure (Ver.8.0.0)

March 07, 2022  
Fleekdrive Co., Ltd.

## Contents

1	Introduction.....	3
2	Advance preparation .....	4
2.1	Confirm the release version of Fleekdrive Desktop. ....	4
3	Update the app.....	4
3.1	Confirm the version of Fleekdrive Desktop that you are using. ....	4
3.2	Update the Fleekdrive Desktop.....	5

## 1 Introduction

This document describes the update procedure and precautions for Fleekdrive Desktop (Ver.8.0.0) released on March 26, 2022.

This document is the update procedure from Ver1.0.4 later.

If you are using earlier than Ver.1.0.4, please upgrade to 1.0.4 and execute the procedure in this document, or uninstall it and use Ver.8.0.0.

## 2 Advance preparation

### 2.1 Confirm the release version of Fleekdrive Desktop.

Log in to Fleekdrive, open the App settings> Fleekdrive Desktop> Fleekdrive Desktop Update setting screen from the Settings menu, and confirm the "Release version".


If the release version is earlier than 8.0.0, the [Update] link will be displayed and click it to release the latest version 8.0.0.

## 3 Update the app

### 3.1 Confirm the version of Fleekdrive Desktop that you are using.


- 1) Right-click the Fleekdrive Desktop icon from the task tray and select "Open Setting".

**Figure 3-1**



- 2) Click the "Version" tab, and the version displayed in "Current version" is the version in use. The following figure is an example when V7.0.0 is using.

**Figure 3-2**




If the version of Fleekdrive desktop you are currently using is 1.0.4 or earlier, upgrade to 1.0.4 and then perform the following procedure, or uninstall it and then install Ver.8.0.0. If your version is 1.0.4 or later, proceed to the next chapter.

### 3.2 Update the Fleekdrive Desktop


- 1) From the task tray, right-click the Fleekdrive Desktop icon and select "Quit Fleekdrive Desktop" to exit the currently running Desktop app once.

**Figure 3-3**



- 2) Right-click on Fleekdrive Desktop from the Start menu and select More > Run as administrator.

**Figure 3-4**



- 3) Right-click the Fleekdrive Desktop icon from the task tray and select "Open Setting".


**Figure 3-5**



- 4) Open the Version tab and click the "Update" button.


*\*It may take some time for the update button to become effective.*

**Figure 3-6**




- 5) When the update confirmation message is displayed as shown below, click on "Yes".

**Figure 3-7**



- 6) The following message is displayed during the update.  
Please wait until the message disappears.

**Figure 3-8**



When the screen in Figure 3-8 disappears, restart your PC.

\* Please note that the upgrade will not be completed until the PC is restarted.